Notes on installing ITU BR Space Applications V10.X

November 6th, 2024

Introduction

As of BR IFIC 3037, as described in Annex 2 of CR, ITU BR Space Applications V10.X software is installed in the standard locations for Windows-compatible software.

Whitelisting Requirements

While in the past there may have been a need for network administrators to whitelist the install directory of BR Space Applications (C:\BR_SOFT), this should no longer be necessary. However, whitelisting some legacy unsigned DLLs may be required.

All ITU-produced executables and DLLs in the ITU BR Space Applications V10.X package have been digitally signed using the ITU's software signing certificate issued by Sectigo RSA Code Signing CA. Most third-party software components have been signed using the appropriate certificates.

In 2024, the ITU BR Space Applications still rely on some legacy components that were produced by Microsoft or acquired from third parties before digital code signing became commonplace. The lists of these unsigned DLLs are provided in <u>Annex 1</u> and <u>Annex 2</u> of the present document. This list will become shorter as the ITU advances in modernizing BR Space Applications software.

Installer Command Line Parameters

The ITU BR Space Applications installer (Installer-v10.X-10.X.y.z.exe) supports the following command line parameters:

Parameter Value	Description
/?	Displays the help message
/silent	Installer will run in silent mode
/appname=[install repair uninstall update] appname can be any of: spacecap spacepub spacecom brsis gims sam gi bc sps ap7capture	Fine-grained control of the action to be applied to each major component of ITU BR Space Applications
/extract3rdpsetups	Extracts third party setups (i.e. Transfinite and Agenium) required by some SAS applications (GIBC) Notes: - In silent mode the installer cannot and will not run these 3rd party setups, they must be installed separately The files are placed in the directory that contains the installer executable The online version of the installer does not contain these files, it downloads them.

Silent Installation

For easier deployment through means such as Software Center, the ITU BR Space Applications V10.X installer supports a silent installation mode, as follows:

Installer-v10.X-10.X.y.z.exe /silent /appname=action ...

Launching the Installer from the command line or from a script

It should be noted that running the installer executable actually starts the installer in a separate process. For this reason, execution of the installer returns immediately (not when installation is complete), and the error level reflects the result of the creation of the child process, not the return code of the installer. In order to wait for the installer to finish you may use the start command with the wait option (or some other means), for example:

start /wait Installer-v10.X-10.X.y.z.exe /silent /sam=install

The return code can be easily obtained from the environment variable **errorlevel**, its value will be 0 on success and a non-zero value in case of failure.

NOTE: The ITU BR Space Applications installer includes two third-party examination packages, from Transfinite and Agenium, for EPFD examination calculations. These packages have separate installers and do not support the silent mode.

Agenium\setup.exe

Transfinite\setup.exe

BR Space Reference Database

The ITU BR Space Applications V10.X require an up-to-date version of the BR Space Reference database to function properly.

When first installed by the ITU BR Space Applications installer, the reference database is located under C:\ProgramData\ITU\BR_Space_v10.X\RefDb (or the directory corresponding to ProgramData on non-English versions of Windows).

It is essential for the reference database to be kept up to date. To that effect, as of BR IFIC (Space) publication 3037, a separate setup executable will be made available, to replace the abovementioned database with the most up-to-date version. It is strongly recommended to put in place a procedure to install the BR Space Reference database that comes with each new BR IFIC (Space) publication.

Troubleshooting Installation Issues

In case of installation issues, please retrieve the log file from the

C:\Program Files (x86)\Itu\BR_Space_v10.X

folder, and send it with a description of the issue to brsas@itu.int

Known Issues

Annex 1 Unsigned DLLs Produced by Microsoft

File Name	Version(s)	Description
dao360.dll	03.60.9756.0	
ieframe.dll	11.00.9600.19130	
	(winblue_ltsb_escrow.1	
	80823-1003)	
microsoft.exchange.webservices.netstandard.dll	1.1.3	
msado25.tlb	6.1.7601.17857	
msadox28.tlb	6.1.7600.16385	
MSBIND.DLL	6.00.8862	
MSBIND.DLL	6.01.9782	
mscal.ocx	8.0.0.5007	
MSRDO20.DLL	6.00.8862	
MSRDO20.DLL	6.01.9782	
msrdo32.dll	1.0.3329	
msvbvm60.dll	6.00.8964	
Msvcirt.dll	6.10.8637.0	
msvcp60.dll	6.00.8972.0	
msvcp60.dll	6.02.3104.0	
msvcp80.dll	8.00.50727.762	
msvcr80.dll	8.00.50727.762	
msvcrt.dll	7.0.7601.17744	
msxml.dll	8.00.7002.0	
oleaut32.dll	2.40.4275	
oledb32.dll	6.1.7601.17514	
OLEPRO32.DLL	2.40	
scrrun.dll	5.8.7601.18283	
stdole2.tlb	6.1.7600.16385	
VB5DB.DLL	6.00.8169	
xolehlp.dll	03.01.00.4414	

Annex 2 Unsigned DLLs from Other Third Parties

File Name	Version	Source	Description
c1flexgridprinter.dll	1.1.1.0	ComponentOne LLC	ComponentOne C1FlexGridPrinter
cximage.dll	7.0.1.3	Pizzolato Davide - www.xdp.it	
dformd.dll	6.1	Compaq Computer Corporation	Compaq Visual Fortran RTL (thread-safe)
dforrt.dll	6.1		Compaq Visual Fortran RTL
gif89.dll	1, 0, 0, 1		Gif89 Module
iconv.dll	1.9		LGPLed libiconv for Windows NT/2000/XP and
			Windows 95/98/ME
ingres.client.dll	2.1.1100.74	Actian Corporation	Ingres .NET Data Provider
interop.adodb.dll	6.1.0.0		Assembly imported from type library 'ADODB'.
interop.adox.dll	2.8.0.0		Assembly imported from type library 'ADOX'.
interop.scripting.dll	1.0.0.0		Assembly imported from type library 'Scripting'.
libxml2.dll	October 2, 2010	https://www.zlatkovic.com/projects/libxml/index.html	XML processor written by Daniel Veillard for the
			GNOME project (see
			https://en.wikipedia.org/wiki/Libxml2).
newtonsoft.json.bson.dll	1.0.1.20722	Newtonsoft	Json.NET BSON .NET Standard 1.3
renci.sshnet.dll	2020.0.1	Renci	SSH.NET
sqlite.interop.dll	1.0.112.1	Robert Simpson, et al.	System.Data.SQLite Interop Assembly
sshnet.security.cryptography.dll	1.3.0	Renci	SshNet.Security.Cryptography for .NET Standard
system.data.sqlite.linq.dll	1.0.113.0	https://system.data.sqlite.org/	System.Data.SQLite for LINQ
tdbg7.ocx	7.0.0288	ComponentOne LLC	True DBGrid Data Bound Grid
tdbgpp7.dll	7.0.24.7	ComponentOne LLC	True DBGrid Pro 7.0 Print Module
todg6.ocx	6.0.0204	ComponentOne LLC	True DBGrid Data Bound Grid
todg7.ocx	7.0.0288	ComponentOne LLC	True OLE DBGrid Data Bound Grid
todgub7.dll	7.0.0.12	ComponentOne LLC	OLE DB Data Source for unbound mode
unity.abstractions.dll	5.11.6.0	Unity Open Source Project	
unity.abstractions.dll	5.11.7.0	Unity Open Source Project	
unity.container.dll	5.11.8.0	Unity Open Source Project	
unity.container.dll	5.11.11.0	Unity Open Source Project	
unity.interception.dll	5.11.1.0	Unity Open Source Project	
xadb7.ocx	7, 0, 0, 4	ComponentOne LLC	XArrayDB ActiveX Object
zipup.dll	1.00.0003	Stan Schultes	ZipUp component
zipup23.dll	2.3	Info-ZIP	Info-ZIP's Zip dll
zlib1.dll	1.2.5	http://www.zlib.net/	zlib data compression library